

Please follow this guide to connect to Hosted ASTS Bridge service to access the test environment of the MOEX Equity & Bond, FX and Money Markets via leased lines:

### **Make sure the connection scheme is correct**

! Access to test environments is allowed only through a fully customized connectivity solution ConnectME.

### **Check the connection addresses**

Execute consecutively the following commands in the command line window:

- To check availability of test servers of the Equity & Bond Market:

```
telnet 91.203.253.46 15014
```

```
telnet 91.203.255.46 15014
```

```
telnet 91.203.253.46 15024
```

```
telnet 91.203.255.46 15024
```

- To check availability of test servers of the FX Market:

```
telnet 91.203.253.46 15010
```

```
telnet 91.203.255.46 15010
```

```
telnet 91.203.253.46 15020
```

```
telnet 91.203.255.46 15020
```

- To check availability of test servers of the Money Market:

```
telnet 91.203.253.46 15012
```

```
telnet 91.203.255.46 15012
```

+ After every command is executed, black screen with a blinking cursor should appear that means successful connection has been made. To execute the next command, press "ctrl"+"C".

- if the error message appears that says *«telnet is recognized as an internal or external command»*, please contact your system administrator to check accessibility of addresses and connection ports.

- if the error message appears that says *"Could not open connection to the host, on port: Connect failed"* please contact your system administrator to receive authorisation to access the pairs of addresses and connectivity ports.

### **Make sure connection setup is correct**

We recommend changing the connection setup when the markets are closed and check in advance network accessibility of connection addresses.

To connect to test gateways of the Equity & Bond Market:

INET environment:

- parameter "HOST" is set to: 91.203.253.46:15014, 91.203.255.46:15014
- parameter "SERVER" is set to: EQ\_TEST
- to connect to clearing, parameter "SERVER" is set to EQ\_TEST\_RISK

UAT environment:

- parameter "HOST" is set to: 91.203.253.46:15024, 91.203.255.46:15024
- parameter "SERVER" is set to: EQ\_UAT
- to connect to clearing, parameter "SERVER" is set to EQ\_UAT\_RISK

To connect to test gateways of the FX Market:

INETCUR environment:

- parameter "HOST" is set to: 91.203.253.46:15010, 91.203.255.46:15010
- parameter "SERVER" is set to: CUR\_TEST
- to connect to clearing, parameter "SERVER" is set to CUR\_TEST\_RISK

UATCUR environment:

- parameter "HOST" is set to: 91.203.253.46:15020, 91.203.255.46:15020
- parameter "SERVER" is set to: CUR\_UAT
- to connect to clearing, parameter "SERVER" is set to CUR\_UAT\_RISK

To connect to test gateways of the Deposits and Credits Market:

INETGKO environment:

- parameter "HOST" is set to: 91.203.253.46:15012, 91.203.255.46:15012
- parameter "SERVER" is set to: GKO\_TEST

**!** If parameter "HOST" has already set to a value that differs from servers with addresses 91.203.253.46 and 91.203.255.46, new setup should be agreed with your system administrator.